

Upgrade CTCopc User Licenses - Modify the Serial Number in Windows' System Registry to Upgrade

40



Control Technology Corporation, Hopkinton, MA • 800.282.5008 • www.ctc-control.com


Summary

This document describes the process of modifying the Window's System Registry to change the existing serial number of CTCopc Server to a new serial number in order to support more licenses. It is very important to backup the System Registry before proceeding.

Run Regedit - Modifying the Registry


NOTE: BACKUP THE REGISTRY BEFORE MAKING ANY MODIFICATIONS TO IT.

Click the **Start** button on the Window's Desktop and select **Run**. Enter `regedit` in the command field to open the system Registry Editor.



Expand the directory structure under the **HKEY_LOCAL_MACHINE** heading to expose the **SOFTWARE** folder. Next, find the **CTC** folder and expand it to expose the **CTCopc** folder. Once selected, the Registry entries will be listed in the Window on the right side. Double-click **serial** and modify the **Value data** to reflect the new serial number.

Under HKEY_LOCAL_MACHINE:



Upon completion of entering the serial number, select **OK** and simply close the Registry Editor. Open CTCopc Server and you will be prompted to enter a valid authorization number which can be obtained from Control Technology Corporation's Customer Support:

Tel. 800.282.5008

Email: customersupport@ctc-control.com